1.	Luminosity Predictions Error! Book	mark not defined.
2.	Luminosity Models	2
a	a. Simple Exponential Model	3
t	o. Modified Exponential Model	
C	c. Simple Inverse Time to Power Model	6
Ċ	d. Modified Inverse Time to Power Model	7
e	e. Chi Square Test of Merit	8
3.	Building a Spreadsheet Tool	
a	n. Spreadsheet Setup	
t	p. External Data Spreadsheets	
	i. SuperTable II	
	ii. Lumberjack Data	
C	e. Luminosity Predictor Spreadsheet: How to Analyze the Data	
	i. Input Data Workbook (Procedure for using the spreadsheet)	
Ċ	d. Luminosity Predictor Spreadsheet: Workbooks in Detail	
	i. LBOE Workbook	
	ii. Lumberjack Data import	
	iii. Input Data for the Luminosity Models	
	iv. The Luminosity Models	
	v. Error Sums	
	vi. Summaries	
	vii. Fits over time	
	viii. Plots	
e	e. VBA Scripts	
	i. Clear All Data Script (Ctrl-Shift-C)	
	ii. Analyze the Data Script (Ctrl-Shift-A)	
	iii. Archive (Write) the Data Script (Ctrl-Shift-W)	
a	Archive Data Files	
	i. Individual store {####}-fit-data.xls files	
	ii. Store-fit-summary.xls file	
4.	Using the Spreadsheet tool to predict Luminosity	
5.	How luminosity fits improve over time	
6. 7	How the Luminosity Fits vary from Store to Store	
7.	References and Useful Sources	45

1. Motivation for Predicting Luminosity Behavior

When planning Collider store turn around times, it would be beneficial to have a tool that could be used anytime in the store to predict the Luminosity behavior later in that store.

We have three existing tools that can help us determine the Luminosity behavior of a store. First, there are models of the Tevatron luminosity¹⁻⁴. Tevatron experts have models that closely predict the luminosity behavior of a store given a few constants including the initial luminosity and luminosity lifetime. If we could determine the correct values for the above mentioned constants early on in the store, we could use a luminosity model to predict the Luminosity behavior over the entire store. Second, we have the SuperTable. Experts examine the luminosity data during the first few hours of each store and calculate an initial luminosity and luminosity lifetime of the store based on a simple exponential fit. These numbers are placed in the SuperTable, and can be easily retrieved in an Excel Spreadsheet. These values provide early feedback as to the initial health of the store. We will see that a simple exponential fit using the SuperTable values does not provide a good long term prediction of the Luminosity behavior of the store, but does provide a good starting point. Last, we have the datalogger. The luminosity readings are datalogged for each store. We can easily export this data to an Excel spreadsheet and plot how the Luminosity has progressed anytime during the store. It may be useful to extrapolate the lumberiack data with the help of our SuperTable data and Luminosity models, to predict the Luminosity behavior of that store.

The goal of this exercise is to build an Excel spreadsheet to help predict the Luminosity behavior of a store. We will construct the spreadsheet so that can be used at anytime during a store. The spreadsheet would use existing Luminosity Models to calculate Luminosity behavior. The initial guesses at the initial luminosity and luminosity lifetimes would be gathered from the SuperTable. The Luminosity Model constants would then be fit to the Lumberjack data for that store. As the store progressed, the tool could be used repetitively to get better and better Luminosity behavior predictions. When the store is finished, we could then examine how accurate the predictions from the various models matched the actual luminosity data.

2. Luminosity Models

We will look at four basic Luminosity Models. The constants for each of these fits are calculated at the end of each store by Elliot McCrory²⁻⁴ and are displayed online at http://mccrory.fnal.gov/tevatronDecayFits/. Future additions of this website will also calculate the fits at different times during the store. In this exercise, we will make a tool to complete these calculations on demand. For each fit, we will show example store data. I have chosen store 4639, which holds our

record for integrated luminosity. The store was long-lived and thus provides a large data sample for us to analyze.

a. Simple Exponential Model

The Simple Exponential fit is what is used to create the luminosity lifetime numbers posted in the SuperTable and is given by Equation (1)

$$L(t) = L_0 e^{-\left(\frac{t}{\tau}\right)} \tag{1}$$

where L(t) is the Luminosity at time t, L_0 is the initial luminosity, t is the time, and τ is the luminosity lifetime.




Figure 2-1: The medium blue and pink traces are the luminosity over time for CDF and D0 for store 4369. The dark blue and red traces are luminosity distributions for CDF and D0 calculated from lifetime and initial luminosity data in the SuperTable II.

Figure 2-1 shows the exponential curve and the lumberjack data for store 4369. The x-axis is time in hours from the beginning of the store, and the y-axis is store luminosity. The dark blue and red curves are the

exponential curves for CDF and D0. The curves are generated using Equation (1) with the initial luminosity and luminosity lifetime numbers from the SuperTable II. The medium blue and pink traces are the luminosity data for CDF and D0 collected from the lumberjack. If the luminosity truly followed the exponential expression in Equation (1) then we would expect the CDF predicted (red line) and actual (pink) to be aligned, and the D0 predicted (dark blue) and actual (blue) to be aligned. We see in the first few hours of the store there is very good agreement between the exponential curve and the lumberjack data; however, as we look later in the store the data soon diverges. If we were to use the exponential fit with the SuperTable numbers to predict the Luminosity later in the store, we would not make a very good prediction.

What happens if we modify the values of initial luminosity and luminosity lifetime in Equation (1) to try to make the experimental and real data better match? The results are shown in Figure 2-2.




Figure 2-2: Here we attempt to match the luminosity data with the Simple Exponential model of Equation (1). We modify the initial luminosity and luminosity lifetime constants in the equation to attempt to make the best fit.

Figure 2-2 shows that the luminosity data and the curve from Equation (1). Using the Excel solver, we were not able to find values for the initial luminosity and luminosity lifetime that would

make the curves generated by Equation (1) match the lumberjack data. We will find better results in our next model.

b. Modified Exponential Model

The second fit is a modification of the exponential fit given in Equation (1). We still use the exponential fit, but assume that the lifetime in the denominator varies with time. We add a constant multiplied by the time raised to another constant to the initial lifetime. The result is shown in Equation (2).

$$L(t) = L_0 e^{-\left(\frac{t}{\tau + \mu t^{\alpha}}\right)}$$
 Equation (2)

where L(t) is the Luminosity at time t, L_0 is the initial luminosity, t is the time, τ is the luminosity lifetime, μ is a positive constant and α is a positive constant.




Figure 2-3: The constants in the modified exponential fit of Equation (2) were modified with the Excel Solver to obtain a very good match with the luminosity data from Store 4369.

Figure 2-3 shows data from Store 4639. We used the Excel Solver to modify the four constants in Equation (2) to match the lumberjack data. Unlike the simple exponential fit, our modified exponential fit gives us very good agreement between the curves and the lumberjack data.

c. Simple Inverse Time to Power Model

Another model, found in "Recycler-Only Operations Luminosity Projections" by Dave McGinnis¹ provides a luminosity fit with only three constants. This equation is given in Equation (3)

$$L(t) = \frac{L_0}{\left(1 + \frac{t}{\mu \tau}\right)^{\mu}}$$
 Equation (3)

where L(t) is the Luminosity at time t, L_0 is the initial luminosity, t is the time, τ is the luminosity lifetime, and μ is a positive constant.




Figure 2-4: Modifying the constants in equation (3) we were able to obtain a fairly good fit for the Store 4369 luminosity data. Careful inspection of the graph shows that the model is least accurate in the first few hours of the store.

Figure 2-4 shows data from Store 4639. We used the Excel Solver to modify the three constants in Equation (3) to match the lumberiack data.

This fit works very well; however, a closer inspection shows that it is not quite as accurate at the beginning of the store as Equation (2). We will take a closer look




Figure 2-5: Comparing how well Equations (2) and (3) fit the data from Store 4639 during the first few hours of the store.

Figure 2-5 shows the same data plotted in Figures 3 and 4, only blown up to look at the first three hours of store 4639. This is an attempt to show the relative accuracy of the two fits at the beginning of the store. We can see that during the first hour and a half of the store, Equation (3) does not quite fit the data as well as Equation (2).

d. Modified Inverse Time to Power Model

Our fourth fit is a modification of the fit given in Equation (3). We will assume that the exponent varies with time. We add a constant multiplied by the time to the initial exponent. The result is shown in Equation (4).

$$L(t) = \frac{L_0}{\left(1 + \frac{t}{\mu \tau}\right)^{\mu + t\alpha}}$$
 Equation (4)

where L(t) is the Luminosity at time t, L_0 is the initial luminosity, t is the time, τ is the luminosity lifetime, μ is a positive constant and α is a positive constant.




Figure 2-6: The constants in the modified time decay fit of Equation (3) were modified with the Excel Solver to obtain a very good match with the luminosity data from Store 4369.

Figure 2-6 shows data from Store 4639. We used the Excel Solver to modify the four constants in Equation (4) to match the lumberjack data. This fit works very well and fits the live data better at the beginning and end of the store than does Equation (3). We will see that Equations (2) and (4) appear to give the best results.

e. Chi Square Test of Merit

When comparing how well each of our models fit the actual luminosity data, it would be helpful to calculate a statistical value representing the merit of the fit. We have chosen a chi square fit as shown in Equation (5)

$$\chi^{2} = \left(\frac{1}{n-C}\right) \sum_{i=1}^{n} \frac{(M_{i} - L(x_{i}))^{2}}{\sigma^{2}}$$
 Equation (4)

where n is the number of lumberjack sample points, C is the number of constants in our luminosity model, M_i is the measured luminosity, L(x) is the calculated luminosity, σ is the sigma of the measured luminosity.

So to calculate our χ^2 value we will simply subtract the calculated luminosity (from our luminosity models) from our measured luminosity (from the lumberjack data). At each point, we will divide by the σ of the luminosity measurement, which is the half height of the error bar of the measured value. We then sum over each of our luminosity readings and divide by the total number of data points less the number of constants in our model.

For this exercise, we will assume that σ values quoted by Elliot McCrory¹, which is $0.006*L_{CDF}$ and $0.0015*L_{D0}$ for CDF and D0 respectively. If the σ values are incorrect, the χ^2 value will be scaled incorrectly, but we will still get a relative comparison between the fits. The smaller the χ^2 value, the better the fit.

3. Building a Spreadsheet Tool

So far we found that three of our fits work well, two of which work extremely well. However, we have only examined data from one store. In addition, we have only looked at store data after the fact. That is we fit all of the data over for the entire store. We have not yet covered how well our equations predict luminosity behavior when only given a limited amount of store data. For example, if we are four hours into a store, can we predict what the luminosity will be at 30 hours into the store? How about if we are six hours into the store? Eight hours? Also, how do the constants in our fits change from store to store? Do they always have similar values, or do they change a lot from store to store? Our goal is to build a tool with Excel to help us answer these questions.

a. Spreadsheet Setup

The default Excel spreadsheet configuration provided in the AD drive image does not have all of the features that we will need enabled. In order to run the spreadsheet we will need to enable the analysis toolpak and solver. Go to Tools -> Add-ins. Check the boxes next to "Solver Add-in," "Analysis ToolPak," and "Analysis ToolPak - VBA."



Figure 3-1: Enable the Solver and Analysis Toolpak.

We next need to verify that our security settings allow us to run Macros. Go to Tools -> Macros -> Security. Select "Medium" and click ok.



Figure 3-2: Set the macro security setting to medium. This allows the user to choose if macros are enabled at the time that a spreadsheet with macros is opened. Be careful! Only enable macros on spreadsheets that you are absolutely sure of their source. Macros are a popular way to spread viruses on Windows computers.

We will also need to setup the VBA editor to run scripts with Solver. With out this step, we would have to run the solver manually to do our analysis. Go to Tools>Macro>Visual Basic Editor. The visual basic editor will open. On the Visual Basic Editor, use Tools>References. A dialog box of references will open. Select Solver.




Figure 3-3: Allowing the Solver to run inside of VBA.

Excel has a great feature that automatically saves your work every 10 minutes. This feature helps the user recover their edits when Excel crashes unexpectedly. Unfortunately, this feature can interfere with our data analysis that we will run from VBA scripts. In order to maximize the resources during our data analysis, we turn off the "Save AutoRecover" feature before we run the data analysis VBA script. Go to Tools -> Options -> Save Tab and uncheck the box next to "AutoRecover." We do not want to forget to turn this feature back on after the data analysis is complete, since the "AutoRecover" feature is very useful.




Figure 3-4: Turn off the "AutoRecover" feature when running an Excel data analysis. Turn "AutoRecover" back on when the data analysis is complete.

Excel should now be configured with all of the settings that we need to analyze our Collider luminosity data!

b. External Data Spreadsheets

We will want to call data from two external spreadsheets.

i. SuperTable II

An Excel version of the SuperTable is readily available for Windows users at \\daesrv\java_engines\files\SupertableExport. Copy this file to the same directory as our master Excel spreadsheet with the filename new supertableII.xls.

One of the Excel lookup functions that we will use requires that the SuperTable spreadsheet have the store numbers listed in ascending order. By default the SuperTable spreadsheet is sorted by store number, but in descending order. Open the SuperTable spreadsheet, then sort all of the data by store number in ascending order, and save the file as an Excel Spreadsheet.

Update the SuperTable as necessary to ensure that you have the data required for the stores that you want to analyze.

ii. Lumberjack Data

We next need to gather the Lumberjack data for the store we are interested in looking at. From Acnet D44 we can start a luminosity plot by going to Users -> Brian Drendel and then Recall -> ShotSetup. The default dataloggers and sample rates for the luminosity readings for this plot are:

- **C:B0ILIM**: .CDF sampled at a 1 minute rate.
- C:D0FZTL: .DZero sampled at a 15 second rate.

We next plot the data from the store in question. Once the plot has been made, we export the data to an Excel spreadsheet using the following steps.

- Select Export Data.
- We only want to export the Luminosity parameters (top two choices). De-select the others and click ok.
- Change the time format for both luminosity parameters from "Lumberjack format" to "hours."
- Select "Excel File"
- Use the name **shot{four digit shot number}.xls**.

The data has been exported, but we still need to make a local copy.

- Open a web browser to http://www-ad.fnal.gov/excel or http://adcon.fnal.gov/pic/capture/excel, depending on if your D44 instance was run from a Linux console or a VMS console.
- Right-click on desired file and save it in the same directory as the Luminosity Predictor spreadsheet. Use the name shot{four digit shot number}.xls.

We now need to cleanup the data file before we can analyze it.

- Open the **shot{four digit shot number}.xls** file (luminosity-predictor.xls should remain closed).
- We want our Luminosity data to start exactly when the luminosity readings show their initial luminosity values. This will give us the best fit later on. D0 data and CDF data should be done separately.
- CDF: Select any data in the first two columns starting with cells A2 & B2 down to where the luminosity signal comes online. Select Edit->Delete and then select to "shift the cells up."
- D0: Select any data in the first two columns starting with cells C2 & D2 down to where the luminosity signal comes to full value. Make sure to include in your selection the

- early luminosity data where the luminosity is not at full value. Select Edit -> Delete and then select "shift the cells up."
- Repeat the above two steps for any zero or bad luminosity data at the bottom of the list (When deleting the cells, select to shift cells up)
- Also scan the file for any bad luminosity data and remove those cells (When deleting the cells, select to shift cells up)
- Save the file as **shot{four digit shot number}.xls** as an Excel workbook.

The data is now in a format ready to be analyzed. Repeat the above procedure for each store that you want to examine.

c. Luminosity Predictor Spreadsheet: How to Analyze the Data

The above section concentrated on getting our data formatted in Excel spreadsheets. We will not modify those spreadsheets. We have a separate Excel Spreadsheet that has the tools built in to analyze that data. We call that spreadsheet **Luminosity-Predictor-Plus.xls**

i. Input Data Workbook (Procedure for using the spreadsheet)

By default, all workbooks in the Luminosity Predictor spreadsheet are protected. Most user interaction with the workbook will occur in the "InputData" workbook. There are interactive buttons connected to VBA scripts that complete a majority of the tasks. To use this spreadsheet, start at the top and work your way down. We will start by selecting a store number, opening the external SuperTable and Lumberjack spreadsheets, verifying the data inside of the external spreadsheets, and then analyzing the data.




Figure 3-5: The Luminosity Predictor Spreadsheet opened to the "InputData" workbook. We start at the top. Click on the interactive button in Cell D1 to choose a Collider store.

Start by clicking on the interactive button in cell D1.




Figure 3-6: Clicking on the interactive button to choose the store number, there are a number of message boxes that the user may encounter. The first message box (upper left) asks the user to input the desired store number. In this example, we want to analyze store 4639 as shown on the left, so we enter the store number (upper right) and then click OK. The VBA script has some error checking, so that if we type a store number not recognized by the VBA script, we get an error (lower left). If we chose a number that is a possible store number, we receive a message box (lower right) with some simple instructions on how to continue.

As shown in Figure 3-6, we are greeted with a message box asking us to input our desired store number. Type the desired store

number and then click OK. In this example, we will type 4369 to analyze store 4369. There is built in error handling if we try to enter a store number outside of the range of the current store numbers. If we chose a valid store number, we get prompted with another message box, as shown in Figure 3-6, providing simple instructions on how to continue. After reading the instructions click OK. We will now step through the steps needed to complete the our data analysis.




Figure 3-7: Once the desired store number is entered, we need to collect the data for this store from the external SuperTable and Lumberjack spreadsheets. Cell range D2:F15 provide feedback on our external spreadsheets. Fields that are not in the desired state are displayed in red text. We start with D2 and work our way down.

Cell D2 reminds the user the name of our SuperTable spreadsheet. If a filename was used, it will not work with the Luminosity Predictor spreadsheet. Cell D3 checks to see if the SuperTable spreadsheet is open and has conditional formatting to notify us as to its status. In Figure 3-7, we see that the SuperTable II file is not open. The user should now open the file.




Figure 3-8: We have selected to analyze Store 4639. Cell D3 shows that the SuperTableII spreadsheet is open, but Cell D4 shows that it is not sorted correctly.

Figure 3-8 shows us the status after we open the SuperTable II file. Cell D4 checks to ensure that the SuperTable has data sorted by store number in ascending order. One of our Excel lookup functions that we will user later requires that the data be sorted in this manner. In this example, the data is not sorted correctly. The user should now sort the data.




Figure 3-9: Cell D3 shows that the SuperTable spreadsheet is open, and Cell D4 shows that it is sorted properly. However, Cell D5 shows that there is no SuperTable II data for Store 4639 in our spreadsheet. We will either need to change store numbers, or replace the SuperTable II spreadsheet.

Figure 3-9 shows us that the SuperTable II file is open and sorted correctly; however Cell D5 shows that the file does not have data for the selected store. The two most likely causes of this problem is that we have selected a store number that does not exist, or our SuperTable II spreadsheet is old or corrupt. Store 4639 is a valid store number, so we replace our SuperTable II spreadsheet with the latest version from \\daesrv\java_engines\files\SupertableExport\. This file is readily available from the user desktop; however, it is not accessible via wireless or from home without a Controls VPN connection.



Figure 3-10: The SuperTable II spreadsheet is open, is sorted properly and has data for Store 4639. We will next need to open our Lumberjack data file for Store 4639.

.

Figure 3-10 shows the results of obtaining the latest SuperTable spreadsheet and having it sorted by store number in ascending order. Cell D3 shows that our SuperTable spreadsheet is open, cell D4 shows that it is sorted properly, and cell D5 shows us that it contains data for Store 4639. We next turn our attention to the Lumberjack data for Store 4639. Cell D6 provides the file name that the Luminosity Predictor is looking for. Follow the earlier given directions on generating the Excel file from D44.




Figure 3-11: Cell D7 shows that we have opened our Lumberjack spreadsheet; however, cells D9 and D13 shows that we had exported the wrong data.

Figure 3-11 shows that we have opened the Store4639.xls spreadsheet; however, Cells 9 and 10 show that we had exported the wrong parameters to our spreadsheet. We must now go back and recreate our Store4639.xls file from our earlier instructions.




Figure 3-12: Cell D7 shows that we have our Lumberjack spreadsheet open for Store 4639, and Cells D9 and D13 show that we have exported the correct devices; however, Cell D8 still shows an error. The most likely cause are the zero Luminosity values at the beginning and end of the store.

In Figure 3-12, Cells D7 and D8 show that we have our Lumberjack spreadsheet open for Store 4639 and we have exported the correct parameters; however, Cell C8 shows that there are some problems with the data. This most likely cause of this problem is the zero luminosity readings at the starting or end of a store. Follow the directions given earlier to trim the errant data from our file.

It should be noted that cells E11 and E14 look at the Lumberjack data file and calculate the sample rate from entries in the time column. The default values are listed and cells will be posted in green if they are equal to those values. The spreadsheet was built so that if you export the lumberjack data from other dataloggers sampled at different rates, the spreadsheet will automatically adjust. Also note that cells C12 and C15 are the sigma of the luminosity reading. This is the half height of the error bar on the reading. At this point, we are using sigma values provided by Elliot McCrory². These numbers are important in that they impact the scaling of our χ^2 quality of fit test.




Figure 3-13: All cells in the range D1:F15 are green, which means that we have both a valid SuperTable II and Lumberjack spreadsheet open for Store 4639. We can now analyze the data from this store. In the box starting at cell A16 are interactive buttons. These buttons point to VBA scripts which do all of the data manipulation and analysis.

Figure 3-13 shows Cells range D2:D5 shows us that the SuperTable II spreadsheet open, is sorted correctly, and contains data from Store 4639. Cell range D6:F16 show us the Lumberjack spreadsheet is open, with the correct luminosity parameters and the data has no zero or error values. We are now ready to analyze the data. In the box starting in cell A16, there are three buttons. These buttons are attached to VBA scripts that do all of the data manipulation and analysis. Simply click on the button to complete the task assigned to that button.



Figure 3-14: The data analysis buttons provide shortcuts to completing all of the necessary data analysis tasks.

The three interactive buttons shown in Figure 3-14 complete the following tasks. More details on the precise steps that each VBA script executes can be found in Section 4 later in this document.

- Clear out the old data: Runs a VBA script that clears all calculated values from cells that may be leftover from previous data analysis runs. This script is run anytime we change which store we want to analyze.
- Analyze the data: Runs a VBA script that analyzes the data.
 This is an interactive script that interfaces the user asking the user over how much lumberjack data to analyze the store and which Tevatron model to use for analysis. This script can be run repeatedly until all of the desired analysis is completed on a store.
- Archive the data: Runs a VBA script to archive the analyzed data. Once we have completed our analysis on a store and want to move on, we archive the data to two Excel spreadsheets: One with all of the analyzed data from this store and one with a selection portion of the analyzed data

d. Luminosity Predictor Spreadsheet: Workbooks in Detail

We covered the procedure of how to complete a round of data analysis using the "InputData" workbook in the Luminosity Predictor spreadsheet. Inside of the Luminosity Predictor spreadsheet are a number of workbooks that compete all of the number crunching. We will now discuss the functions of each of these workbooks.

i. LBOE Workbook

Many of the miscellaneous functions needed for the Luminosity Predictor spreadsheet are handled in the "*LBOE*" workbook (LBOE is an old acronym borrowed from AD\Controls that stands

for "little bit of everything"). Cell Range B12:E16 contain initial luminosity, luminosity lifetime and store duration numbers that are imported from the SuperTable spreadsheet. Anytime we need any of these numbers in this spreadsheet, we point back to these cells. This is done so that if our source of these parameters ever changes, we only have to edit this location. The title of this table contains the store number obtained from Cell D1. The title changes automatically when the user inputs a new store number.

SuperTablell Data for 4639					
C:B0ILUM C:D0FZTL					
L ₀ = Luminosity (e30) =	179.96	151.27			
τ = Lifetime (hr) =	6.42	7.27			
Store Length in hours =	37.01				

Figure 3-15: Cell Range B12:E16 displays of the data that is imported from the SuperTable II.

The SuperTable II numbers in Figure 3-15 are obtained by doing a VLOOKUP of data in our SuperTable II spreadsheet. The VLOOKUP command looks for the store number in the first column of the SuperTable II spreadsheet. Once the store number is found, the function collects the data for that row in columns #7 (store duration), #13 (SDA CDF initial luminosity), #14 (SDA D0 initial luminosity), #23 (CDF luminosity lifetime), and #24 (D0 luminosity lifetime). When the store number is changed from Cell D1, the VLOOKUP function automatically changes the data in this table to match the new store number.

The VLOOKUP function requires that the first column of the SuperTable II spreadsheet be sorted in ascending order. This explains why we sorted the file earlier.

Lumberjack data from Store4639.xls					
	C:B0ILUM	C:D0FZTL			
Valid Data Points (Last Row) =	2171	8837			
Lumberjack Estimated Store Hours =	35.02	36.82			

Figure 3-16: Cell Range B18:B21 examines the lumberjack data file. It determines the number of valid data points and calculates an estimated time of available data.

Figure 3-16 shows cell range B18:B21 on the "*InputData*" Workbook. Here we look at the lumberjack luminosity data. The Excel count function is used to count the number of valid luminosity data points. Using the sample rate from Cells F7 and F9, we calculate an estimated time of store data that we have to analyze. If all of the data is good, these times should be close to the store duration number in cell D16 that was obtained from the SuperTable.

# of Lumberjack Data Points at different times							
		C:B0ILUM	C:D0FZTL				
Datalogg	ger samples/hour	60	240				
1 hours	1	62	242				
2 hours	2	122	482				
4 hours	4	242	962				
6 hours	6	362	1442				
8 hours	8	482	1922				
10 hours	10	602	2402				
12 hours	12	722	2882				
14 hours	14	842	3362				
16 hours	16	962	3842				
18 hours	18	1082	4322				
20 hours	20	1202	4802				
22 hours	22	1322	5282				
24 hours	24	1442	5762				
26 hours	26	1562	6242				
28 hours	28	1682	2 6722				
30 hours	30	1802	7202				
All Data	EOS	1822	7314				
T. 0	4 = 701 11	D00 E40 :	11 ((T (D				

Figure 3-17: The cell range B23:E42 in the "InputData" workbook contains the last row of data at different slices in time.

Cell range B23:E42 calculate how many datalogger data points exist at various hour breakpoints. This data is used to build the cell names that correspond to different time slices of the data.

	Simple Ever	Simple Exponential		Cell locations on our		Inverse Time Decay	
Hours	C:BOILUM	C:D0FZTL	C:BOILUM	C:D0FZTL	C:BOILUM	C:DOFZTL	
1 hour	SimpleFitlE62	SimpleFitiG240	ModSimpleF#E62	ModSimpleFitiG240	1-1FME62	3-1Fit19240	
2 hours	SimpleFittE122	SimpleFitIO478	ModSimpleF#E122	ModSimpleFitIG478	1-1F#1E122	3-1Fit90478	
4 hours	SimpleFittE242	BimpleFitiG954	ModSimpleFi8E242	ModSimpleFitiG954	1-1F#1E242	5-1F)(DG954)	
5 hours	SimpleFittE362	SimpleFittO1430	ModSimpleFifE362	ModSimpleFitIO1430	1-1F#1E362	1-1Fit101430	
hours	SimpleFittE482	SimpleFittG1906	ModSimpleFifE482	ModSimpleFittG1906	1/1F//1E482	3-1Fif901906	
10 hours	SimpleFittE602	SimpleFitlG2382	ModSimpleFifE602	ModSimpleFittiG2382	1-1F#1E602	1-1FIf102382	
12 hours	SimpleFittE722	SimpleFitIG2958	ModSimpleFifE722	ModSimpleFittG2858	1-1FmE722	1-1Fit002858	
4 hours	SimpleFittE842	SimpleFitt93334	ModSimpleF#E842	ModSimpleFitt03334	1-1FME842	1-1FIf903334	
6 hours	SimpleFittE962	SimpleFittG3810	ModSimpleF#E962	ModSimpleFitt03810	1-1F#1E962	5-1F)(503810	
t8 hours	SimpleFitE1082	SimpleFiftG4286	ModSimpleFifE1082	ModSimpleFithG4286	1-1F#1E1882	5-1Fif90-4286	
20 hours	SimpleF#E1202	SimpleFittO4762	ModSimpleFifE1202	ModSimpleFitt04762	1-1FIRE1202	1-1Fitt04762	
22 hours	SimpleFittE1322	SimpleFitt05238	ModSimpleFifE1322	ModSimpleFittG5238	1/1FME1322	1-1Fit195238	
24 hours	SimpleFittE1442	SimpleFitl05714	ModSimpleFifE1442	ModSimpleFitt05714	1-1FINE1442	1-1Fif905714	
% hours	SimpleFittE1582	SimpleFittG6190	ModSimpleFitE1562	ModSimpleFittG6190	1-1F#1E1582	1-1Fit1G6190	
8 hours	SimpleFitE1682	SimpleFitlG6666	ModSimpleFifE1682	ModSimpleFitIG6666	1-1F#IE1882	3-1FIf106666	
0 hours	SimpleFittE1802	SimpleFitIG7142	ModSimpleFifE1802	ModSimpleFitt07142	1-1F#1E1802	3-1Fit907142	
All Data	SimpleFitE2171	SimpleFiflG8837	ModSimpleF#E2171	ModEimpleFitlG6837	1/1FINE2171	%1Fit1G8837	

Figure 3-18: Cell range B44:L63 contains the cell names at various slices in time for the workbooks that calculate the difference between our luminosity curves and the lumberjack data. Due to space limitations, not all of the columns in this spreadsheet are shown.

Cell Range B44:L63 contains the cell names for our data fit spreadsheets at the time slices specified in Figure 16. We will need these cell names later to calculate errors between the predicted and actual data at various hour breakpoints.

Plot Labels
Store 4581 SuperTablell Numbers (C:B0ILUM & C:D0FZTL)
Store 4581 Simple Exponential (C:B0ILUM & C:D0FZTL)
Store 4581 Modified Exponential (C:B0ILUM & C:D0FZTL)
Store 4581 Inverse Time to Power (C:B0ILUM & C:D0FZTL)
Store 4581 Modified Inverse Time to Power (C:B0ILUM & C:D0FZTL)
Store 4581 C:BOILUM Simple Exponential Fit at various store times
Store 4581 C:BOILUM Modified Exponential Fit at various store times
Store 4581 C:B0ILUM Inverse Time to Power Fit at various store times
Store 4581 C:BOILUM Modified Inverse Time to Power Fit at various store times
Store 4581 C:D0FZTL Simple Exponential Fit at various store times
Store 4581 C:D0FZTL Modified Exponential Fit at various store times
Store 4581 C:D0FZTL Inverse Time to Power Fit at various store times
Store 4581 C:D0FZTL Modified Inverse Time to Power Fit at various store times

Figure 3-19: Plot labels.

The labels for our plots are concatenated by colleting data from various cells in the spreadsheet. The resulting plot titles are output to cell range B65:F78 in the "InputData" workbook. If we change store numbers and other data, the plot labels automatically adjust.

# of constants in each fit							
	Simple Exponential	Modified Exponential	Inverse Time Decay	Modified Inverse Time Decay			
# Constants	2	4	3	4			

Figure 3-20: Cell range B84:F86 shows the number of constants in luminosity model.

The last data displayed on the "InputData" workbook are the number of constants for each available luminosity model. We will need these numbers to help calculate our χ^2 test of merit between our luminosity curve and our lumberjack data. These numbers are manually entered.

ii. Lumberjack Data import

As discussed earlier, Lumberjack data is imported from another Excel Spreadsheet named **Store**{Store Number}.xls, where "Store Number" is obtained from Cell D1. When analyzing the data from this store, we do not modify the original **Store**{Store Number}.xls file. Instead, we mirror the data and manipulate it inside of the Luminosity Predictor spreadsheet.

	Α	В	С	D
1	Time	C:B0ILUM	Time	C:D0FZTL
2	3.50028	183.409	3.49	158.642
3	3.51722	180.527	3.49417	158.733
4	3.53389	183.267	3.49833	158.685
5	3.55056	179.874	3.5025	158.105
6	3.56722	180.185	3.50667	157.913
7	3.58389	179.617	3.51083	157.893
8	3.60056	178.165	3.515	157.653
9	3.6175	177.936	3.51917	157.615

Figure 3-21: Lumberjack data for store 4639 is stored in Store4639.xls.

Store{*Store Number*}.xls has four columns of data that we need to import that represent Luminosity/Time pairs for both experiments. We will complete this using the "*ReformatLumberjack*" workbook in our Luminosity Predictor spreadsheet.

	Α	В	С	D	Е			
1	Counter	Generated cell names for lumberjack file Store4639.xls						
2	1	store4639.xls!A1	store4639.xls!B1	store4639.xls!C1	store4639.xls!D1			
3	2	store4639.xls!A2	store4639.xls!B2	store4639.xls!C2	store4639.xls!D2			
4	3	store4639.xls!A3	store4639.xls!B3	store4639.xls!C3	store4639.xls!D3			
5	4	store4639.xls!A4	store4639.xls!B4	store4639.xls!C4	store4639.xls!D4			
6	5	store4639.xls!A5	store4639.xls!B5	store4639.xls!C5	store4639.xls!D5			
7	6	store4639.xls!A6	store4639.xls!B6	store4639.xls!C6	store4639.xls!D6			
8	7	store4639.xls!A7	store4639.xls!B7	store4639.xls!C7	store4639.xls!D7			
9	8	store4639.xls!A8	store4639.xls!B8	store4639.xls!C8	store4639.xls!D8			
10	9	store4639.xls!A9	store4639.xls!B9	store4639.xls!C9	store4639.xls!D9			
11	10	store4639.xls!A10	store4639.xls!B10	store4639.xls!C10	store4639.xls!D10			
12	11	store4639.xls!A11	store4639.xls!B11	store4639.xls!C11	store4639.xls!D11			

Figure 3-22: Columns A through E of the "*Reformat Lumberjack*" workbook.

The A Column contains a counter to help construct names in the B, D, F, and H Columns. The B, D, F, and H Columns in the Luminosity Predictor construct the file and cell names for the A, B, C, and D Columns of **Store**{*Store Number*}.xls. These names change depending on what store number we have entered in cell D1 of the "*InputData*" workbook. If we change the store number, the names in these cells automatically change.

	F	G	Н		J	K	L	М
1	Raw Tin	ne/Lumin Store4	-	nirs for		culated Ti		-
2	Time	C:B0ILUM	Time	C:D0FZTL	Time	C:BOILUM	Time	C:D0FZTL
3	19.1969	178.701	19.1889	151.935	0.00	178.70	0.00	151.94
4	19.2136	179.427	19.1931	151.917	0.02	179.43	0.00	151.92
5	19.2303	177.914	19.1972	151.563	0.03	177.91	0.01	151.56
6	19.2469	176.607	19.2014	151.749	0.05	176.61	0.01	151.75
7	19.2636	170.58	19.2056	151.357	0.07	170.58	0.02	151.36
8	19.2803	177.148	19.21	151.266	0.08	177.15	0.02	151.27
9	19.2972	175.901	19.2142	151.179	0.10	175.90	0.03	151.18
10	19.3139	174.091	19.2183	151.007	0.12	174.09	0.03	151.01
11	19.3306	173.243	19.2225	151.041	0.13	173.24	0.03	151.04

Figure 3-23: Columns F through M of the "ReformatLumberjack" workbook.

The C, E, G, and I Columns of the "*Reformat Lumberjack*" workbook use the Excel INDIRECT command with the values in columns B, C, D and E. This provides a mirror of the **Store**{*Store Number*}.xls A, B, C, and D Columns. Again, if we change the desired store number from cell D1 of the "*InputData*" workbook, these cells change to look at the spreadsheet from that store.

Columns F through I gives us time/luminosity pairs, but they are not quite ready for data analysis. Note that the times in columns F and I are in hours starting at the hour that the store began. We instead want to construct our time columns to be the number of hours since the store started. We use the following IF statement to construct the time columns.

```
=IF(AND(ExtractLumberjack!C3>0, NOT(ExtractLumberjack!C3=" "),NOT(ExtractLumberjack!C3=" ")), ExtractLumberjack!C3-ExtractLumberjack!$C$3, NA())
```

The verification that a cell does not have 7 or 8 blank spaces was added after it was discovered that sometimes the Lumberjack data has cells with 7 or 8 blank spaces where no real data exists. If this check is not added, some of my later calculations are give errors since they do not know how to handle the empty spaces.

We now have successfully imported our lumberjack store data. Columns J through M of the "*Reformat Lumberjack*" workbook are now time/luminosity pairs for CDF and D0 with the time columns starting at zero. Now that we have the luminosity data for a specified store, we will try to fit our Collider luminosity model equations to the data to see how well we can make them agree.

iii. Input Data for the Luminosity Models

We now turn our attention to building curves for the four luminosity models that were outlined in Equations (1) through (4) of Section 2 in this document.

We first create a location for the constants in our four models. We do this on the "FitNumbers" Workbook.




Figure 3-24: The "FitNumbers" workbook in the Luminosity Predictor spreadsheet.

Columns B through F are the constants for CDF and columns G through K are the same for D0. Recall from Equations (1) through (4), that we had.

- L_0 = Initial Luminosity
- τ = Luminosity Lifetime
- μ = constant (if applicable)
- α = constant (if applicable)
- χ^2 = chi square test of merit (We will see later these cells have a blue background because they are mirrored from another location in this spreadsheet).

Each row of the "FitNumbers" workbook contains constants from a different Collider luminosity model.

- Row 4: SuperTable II numbers that were derived from the Simple Exponential Fit of Equation (1). These cell backgrounds are colored grey since we do not change these values.
- Row 5: Simple Exponential Fit of Equation (1)
- Row 6: Modified Exponential Fit of Equation (2)
- Row 7: Time Decay Model of Equation (3)
- Row 8: Modified Time Decay Model of Equation (4)

It is important to note that we never manually change anything in this workbook. We will see later that a VBA macro is called that does all of the data analysis for us. The script will automatically minimize the χ^2 value for each model by varying the constants for that model

iv. The Luminosity Models

We have separate workbooks with Luminosity/Time pairs for each luminosity model. We take each time from our "ReformatLumberjack" workbook and calculate the Luminosity at each point based on Equations (1) through (4) and the constants from the "FitNumbers" workbook. The result is columns A through E in each of our model workbooks contain the time/luminosity pairs from the model equation. Columns E and F contain the square of the differences between the measured luminosity and the luminosity calculated from our model, divided by the square of the sigma of our measurement. Equations (5) and the data from these columns will be used to determine our χ^2 quality of fit test. We will now examine the workbooks from each luminosity model.

1. SuperTable II Prediction:

We start by plugging in the initial luminosity and luminosity lifetime numbers into our simple exponential decay model that was given in Equation (1). This is done in the "SuperTable Predictions" Workbook.

	А	В	С	D	E	F
	Store 4639 SuperTable Prediction			redictions	Measured	- Predicted
1		L(t) = L	$L_0 e^{-\left(rac{t}{ au} ight)}$		$\frac{(M_i - C_i)^2}{C_i}$	$\frac{L(\mathbf{x}_i))^2}{\sigma^2}$
2	hours from start of store	C:B0ILUM Init Lum=179.96 Lifetime=6.42		C:D0FZTL Init Lum=151.27 Lifetime=7.27	C:BOILUM Errors $\frac{(M_i - L(x_i))^2}{\sigma^2}$	C:D0FZTL Errors $\frac{(M_i - L(x_i))^2}{\sigma^2}$
3	0.00	179.960	0.000	151.270	1.379	8.514
4	0.02	179.492	0.004	151.183	0.004	10.386
5	0.03	179.026	0.008	151.097	1.086	4.194
6	0.05	178.564	0.012	151.010	3.410	10.537
7	0.07	178.100	0.017	150.923	53.985	3.656
8	0.08	177.637	0.021	150.832	0.212	3.665
9	0.10	177.170	0.025	150.744	1.446	3.671
10	0.12	176.710	0.029	150.659	6.287	2.354

Figure 3-25: The "SuperTable-Prediction" workbook calculates time/luminosity pairs in columns A through D. The times are a mirror of the times in our lumberjack date file. Columns E and F show the square of the differences between the measured and predicted divided by the square of the sigma of our measurement. These columns will be used to determine our χ^2 merit of fit.

This method was determined not to be very useful, but is still completed for comparison sake.

2. Simple Exponential Fit

The "SimpleFit" Workbook uses Equation (1) and the corresponding input parameters from the "FitNumbers" Workbook to create Luminosity/Time pairs. The "FitNumbers" values are modified via a script to optimize the agreement between the lumberjack luminosity values and the calculated luminosity values.

	А	В	C	D	E	F
		Simple Ex	tial	Measured	- Predicted	
1		L(t) =	$L_0e^{-\left(\frac{t}{\tau}\right)}$		$M_i - M_i$	$\frac{L(\mathbf{x}_i))^2}{r^2}$
2	hours from store start	C-BOLUM Int Lun=117.56 Lifetime=19.2 chi su=255.59	hours from store start	C:D0FZTL Init Lum= 102.04 Lifetime=19.27 chi sq=4129.08	C:BOILUM Errors $\frac{(M_i - L(x_i))^2}{\sigma^2}$	C:D0FZTL Errors $\frac{(M_z - L(x_t))^2}{\sigma^2}$
3	0.00	117.5560979	0.000	102.042956	3252.101	47925.253
4	0.02	117.4538781	0.004	102.0207126	3313.818	47944.765
5	0.03	117.3517471	0.008	101.9990034	3218.706	47529.553
6	0.05	117.2503156	0.012	101.9767696	3137.769	47812.341
7	0.07	117.1483617	0.017	101.9545406	2725.450	47348.868
8	0.08	117.0464963	0.021	101.9312583	3197.390	47275.982
9	0.10	116.9435012	0.025	101.9090392	3120.606	47206.193
10	0.12	116.841814	0.029	Transportation of terral property of the second	3003.886	47025.539
11	0.13				2954.785	47112.009

Figure 3-26: The "SimpleFit" workbook calculates values for the Simple Exponential luminosity model. Columns A and C mirror the time values in our lumberjack file. Columns B and D are the calculated CDF and D0 luminosity based on the simple Exponential Model given in Equation (1) with the constants from the "FitNumbers" workbook. Columns E and F calculate an error between the measured and calculated luminosity numbers. These errors are used to calculate our χ^2 quality of fit test.

3. Modified Exponential Fit

The "ModSimpleFit" Workbook uses Equation (2) and the corresponding input parameters from the "FitNumbers" Workbook to create Luminosity/Time pairs. The "FitNumbers" values are modified via a script to optimize the agreement between the lumberjack luminosity values and the calculated luminosity values.

	Α	В	С	D	Е	F		
	Α	Modified E		Measured - Predicted				
1		$\frac{(M_i - 1)^2}{\sigma}$	$L(x_i)^2$					
	from store start	C:BOILUM Init Lum=181.92 Lifetime=3.33 u=1.79 a=0.56	from store start	C:D0FZTL Init Lum=153.25 Lifetime=4.56 u=1.34 a=0.62	C:BOILUM Errors $\frac{\left(M_i - L(x_i)\right)^2}{\sigma^2}$	C:D0FZTL Errors $\frac{(M_i - L(x_i))^2}{\sigma^2}$		
3	0.00	chi sq=1.19 181.9231475	0.000	chi sq=6.69 153.249986	9.031	33.292		
4	0.00	181.0608569	0.004	153.249308	2.303	27.416		
5	0.03	180.2435268	0.008		4.762	38.586		
6	0.05	179.4605122	0.012	152.8381039	7.252	22.893		
7	0.07	178.6965439	0.017	152.7020009	62.890	35.096		
8	0.08	177.9529163	0.021	152.5603765	0.573	32.543		
9	0.10	177.2186242	0.025	152.4260308	1.559	30.240		

Figure 3-27: The "*ModSimpleFit*" workbook calculates values for the Modified Exponential luminosity model of Equation (2). Columns A and C mirror the time values in our lumberjack file. Columns B and D are the calculated CDF and D0 luminosity based on the Modified Exponential Model given in Equation

(2) with the constants from the "FitNumbers" workbook. Columns E and F calculate an error between the measured and calculated luminosity numbers. These errors are used to calculate our χ^2 quality of fit test.

4. Inverse Time to Power Fit

The "*t-1Fit*" Workbook uses Equation (3) and the corresponding input parameters from the "*FitNumbers*" Workbook to create Luminosity/Time pairs. The "*FitNumbers*" values are modified via a script to optimize the agreement between the lumberjack luminosity values and the calculated luminosity values.

	А	В	С	D	Е	F
		Inverse T	_	Measured -	Predicted	
1		L(t) = -	$M_i - C$	$\frac{L(x_i))^2}{r^2}$		
	hours from store start	C:B0ILUM Init Lum=166.8 Lifetime=7.56 u=1.37	hours from store start	C:D0FZTL Init Lum=144.81 Lifetime=7.56 u=1.36	C:BOILUM Errors $\frac{(M_i - L(x_i))^2}{\sigma^2}$	C:D0FZTL Errors $\frac{(M_i - L(x_i))^2}{\sigma^2}$
2	0.00	chi sq=6.41	0.000	chi sq=49.46	400.007	070 405
3	0.00	166.7953217	0.000	144.8132942	123.297	976.495
4	0.02	166.4277995	0.004	144.7328816	145.799	
5	0.03	166.0616745	0.008	144.6544582	123.278	923.430
6	0.05	165.6991192	0.012	144.5741985	105.965	993.541
7	0.07	165.335758	0.017	144.4940159	26.255	913.773
8	0.08	164.9737717	0.021	144.4100978	131.192	912.986
9	0.10	164.6088424	0.025	144.330073	114.476	912.178
10	0.12	164.2496	0.029	144.2520277	88.768	889.345
11	0.13	163.8917104	0.034	144.1721547	80.934	919.169
12	0.15	163.5372974	0.038	144.0923583	144.389	888.627
13	0.17	163.1820837	0.042	144.0145357	126.259	845.655

Figure 3-28: The "*t-1Fit*" workbook calculates values for the Time Decay luminosity model of Equation (3). Columns A and C mirror the time values in our lumberjack file. Columns B and D are the calculated CDF and D0 luminosity based on the Time Decay Model given in Equation (3) with the constants from the "*FitNumbers*" workbook. Columns E and F calculate an error between the measured and calculated luminosity numbers. These errors are used to calculate our χ^2 quality of fit test.

5. Modified Inverse Time to Power Fit

The "*t-1ModFit*" Workbook uses Equation (4) and the corresponding input parameters from the "*FitNumbers*" Workbook to create Luminosity/Time pairs. The "*FitNumbers*" values are modified via a script to optimize the agreement between the lumberjack luminosity values and the calculated luminosity values.

		А	В	С	D	Е	F
		ľ	Modified Inver	Measured	- Predicted		
1			$M_i - M_i = 0$	$L(\mathbf{x}_i))^2$			
2	2	Hours Holli store start	C:B0ILUM Init Lum=176.83 Lifetime=5.58 u=0.79 a=0.005 chi sq=1.37	hours from store start	C:D0FZTL Init Lum=150.55 Lifetime=6.17 u=0.9 a=0.004 chi sq=6.94	C:BOILUM Errors $\frac{(M_i - L(x_i))^2}{\sigma^2}$	C:D0FZTL Errors $\frac{(M_i - L(x_i))^2}{\sigma^2}$
3	3	0.00	176.8345416	0.000	150.550231	3.030	36.920
4	1	0.02	176.3068004	0.004	150.4477428	8.400	41.572
. 5	5	0.03	175.7825153	0.008	150.3478331	3.987	28.570
6	6	0.05	175.2647593	0.012	150.2456278	1.605	43.621
7	7	0.07	174.7472591	0.017	150.1435652	16.578	28.566
8	3	0.08	174.2331092	0.021	150.0367952	7.521	29.348
9		0.10			149.9350239		

Figure 3-29: The "t-1ModFit" workbook calculates values for the Modified Time Decay luminosity model of Equation (4). Columns A and C mirror the time values in our lumberjack file. Columns B and D are the calculated CDF and D0 luminosity based on the Modified Time Decay Model given in Equation (4) with the constants from the "FitNumbers" workbook. Columns E and F calculate an error between the measured and calculated luminosity numbers. These errors are used to calculate our χ^2 quality of fit test.

v. Error Sums

We recall that our χ^2 quality of fit calculations in Equation (5) sums the error terms that we calculated in the workbook for each model and then divides that number by the number of data points minus the number of constants in the model equation. We have a separate χ^2 calculation for each luminosity model. We don't end there.

One of the goals of this project is to also look at how these fits project the luminosity with varying lengths of lumberjack data. For example, we may want to see how well we project the luminosity after the first two hours of data, then after four hours of data, etc. We will have a different χ^2 calculation for every time slice of data we want to examine. We don't want to have to manually trim our lumberjack data every time we want to look at a different time slice of data, so we'll make the Luminosity Predictor spreadsheet do the work for us.



Figure 3-30: The "ErrorSums" workbook makes all of the possible χ^2 calculations based on the numbers input to the "FitNumbers" workbook and the errors calculated for each time/luminosity pair in the model workbooks.

The "ErrorSums" workbook calculates the χ^2 quality of fit number for each fit at each possible time slice based on the numbers input in the "FitNumbers" workbook and the errors calculated in the luminosity model workbooks. A script automatically copies the correct χ^2 values depending on what fit the spreadsheet user is attempting to make.

vi. Summaries

After we complete our first set of fits at one time slice, we will want to save that data away so that we can move on to our next set of fits at a different time slice for the current store. The "D0_Results" and "CDF_Results" are used to store the data after we complete a fit.

	, A	- 15	- 0	H II	M	NK	84	1.0	DR		A	9	н	Ц	M	NK	8 P	TQ	UR
1	s foresidad W4689												s f Z	or EBOtic	hild M	4639			
L = L								Leg	0	ī	(g) Δ() Le ^{lai}	(f) -	$\left(1 + \frac{I_0}{\mu}\right)^2$	$= \frac{\lambda_0}{\left(1 + \frac{s}{\mu r}\right)^{\mu \theta}}$	<u>.</u>	h		
milit	н		59 B	hidded Sm	ngde 1	III M	addread 14 I of			mβle			SI N	odMed Sin	nple 1	TFI M	odMed 18 FR		
. 4	72	10	1.	10	12.	pg2.	pg7.	is 1.0	χλn	4	12	ш	T	ш	0.	μχ2	µ32	cc LU	32 t
11.55	: inpresentation /	178.88								6.92	8 6677 105087	179,96							
3.00	Ouri290/5944	187.90	1893	167680	0.7996	1.3739	0.7892 90		1,379.0	N BIII	Constant Maria	110 507	5703	17809000	11.55569	1 3000	HORSE ST		10085
100	2 hours 1313	179,090	5.860 9.960		2000 2000	0.835	0.738213	0.700244	1,7556	004	1 hourt 7130 2 hours 1313	178.664	9,003	1780800	21800	3.000	0.336503	0.780980	1.75.60
36.	4 huma 8454	175090	A1002	1730000	2000	U.835	U.838413	1031.0	1.39.50	686	A house CACA	173,946	4792	1790893	0.203	0.737	0.540090	0.091373	0.3089
0.74	6 hout5.1410		\$30EB		0.708	0.795	0.039381	0.791426	0.88.85	10.00	R hunde 1410	10000	10-0611	17/11/00/2	31,7101	0.030	11.5036 (11)	10191919	1114115
16.40	Ubur/9/4139	100101	NUMES.		31.HEK	11.000	11.5050 (11	103000	11 (1000)	0.49	8 hou25,0129	173,951	9.992	178,083	DIST	0.843	0.900081	0.790388	0.7469
0.70	10 ho40:0913	178,840	1 (0.1750)		DISE	0.897	0.600210	0.708 60	0.74.97	550	111000001513	1500,000	THESTH	17.0495	313311	IIII	U BIM 15	TUNCK	0.7430
611	121(00/07/20	1590363	18995		31995	1800	11 868622	1000000	II HACKING	ATM.	12 htss:7792	174.397	14900	178,990	0.0079	0.933	0.049022	0.787343	0.6566
230	14 hottgp4972	178.313	12/23/3		0.003	0.908	0.600771	0.795780	0.6554	20	14 0 000 000 000	159 313	13590	1,040,046	11811	386	0.080(7)	10000	1111854
9.5	18 0 000 000 000	148 S-	1204.5		HINE	1.000	0.000000	10000	II HALL B	978	16 hc87c3869	149,938	12393	170,366	EDD012	1,02	0.649381	0.797388	0.6808
710	18 hb00d 502	140952	13350		0.044	1,053	0.677033	0.79874	0.6989	400	1000066502	1470857	100999	174.662	81364	1 lbs	0.898 (0.1	110011104	II HMTM
G (6	DITHOMSORIE	1 9 50 5	1.002008		HUSBII	1.1885	IL DOM: UZ	1000000	II HMHX	479	20 http://s760	139,906	18700	173,790	0.308	1,095	0.670002	0.79673	0.6982
038	22 htt87c4913	130.372	193434	17.3.807	0.000	1.032	0.286506	0.79501	0.7906	IMM	2210069910	108 307	159564	172088	11/19/15	1.100	11.05165104	HI WILLIAM	III CMITIS
.038	24 HOMENITT	100 007	1,58,9675	17.09888	81961	1.108	11 0889 114	1000111	11.05.00	726	24 hb58:3811	123,34%	19876	1711.0002	0.078	1.073	0.894804	0.785(10)	0.7921
30	26 hb7254341	130.368	181036	1711.282	0.782	1.802	0.7236 80	0.000393	0.8532	340	28 000000001	100 300	180009	17.00000	81505	1.000	H ASHIII	TENERS SET	11115017
59/10	70 0000 CD/S	174 840	1885566	17111884	100000	1 10 11	11 (7.88 41)	100004 007	1111955	940	28 htt85/7845	127,937	18824	170LEGE	0.54%	1.839	0.238848	0.706 87	0.8939
423	30 h20n :3429	122,030	13399	16/3.18044	70.003	1.287	0.512027	0.788 26	0.9926	4980	30000000000		1.10399	1841188	415681	1.300	II 80 6 27	HUIR 28	II SHOW
180	AU 1 D&A 5944	110.556	120084	1194.095	41585	1.370	H BIRM SH	1000000	10000	100	All 0285,9944	181.929	19:393	168,792	70.DED	1.378	0.882 90	0.782333	1.97.57

Figure 3-31: Summary of all CFD fits that were completed for Store 4639. If we chose not to complete certain fits for that store, those cells will be empty.



Figure 3-32: Summary of all D0 fits that were completed for Store 4639. If we chose not to complete certain fits for that store, those cells will be empty.

Figures 3-31 and 3-32 are summary spreadsheets that contain all of the fit model constants and c2 values at each time slice. Each row represents a different slice in time. For example, if we fit the store with 2 hours of lumberjack data, those fit values would be copied into row 8 of the spreadsheet. Row 6 is a mirror of whatever the current fit is on "FitNumbers" workbook. Row 23 is for all store data after the store has been completed.

vii. Fits over time

If data is fit over multiple time slices, it may be worthwhile to be able to plot the data for each of the fits over time to see how the predicted luminosity curves change over time. This could help us answer the following question? After how many hours of

lumberjack data would we expect to be able to make an accurate prediction of the luminosity value at the end of the store?

To add this functionality an additional workbook for each Tevatron luminosity model was added. The new workbooks take all of the values for that fit from the "CDF_Results" and "D0_Results" workbooks and create time/luminosity pairs for plotting. In this case the times are constructed from 0 to 40 hours at 0.05 hour increments. Figures 33 through 36 show the workbooks for our four luminosity models outlined in Equations (1) through (4).

	А	В	С	D	Е	F	G	Н	I					
	Simple Exponential fit at various times during the store													
1	$L(t) = L_0 e^{-\left(\frac{t}{\tau}\right)}$													
	t	Predicted Pred												
2	(hours)	rs)												
	from store start	Current Fit Init Lum=118 Lifetime=19.2	Current Fit Init Lum=102 Lifetime=19.27	1 hour Init Lum=179 Lifetime=5.65	1 hour Init Lum=151 Lifetime=6.33	2 hours Init Lum=177 Lifetime=6.3	2 hours Init Lum=150 Lifetime=7.1	4 hours Init Lum=173 Lifetime=7.57	4 hours Init Lum=147 Lifetime=8.03					
3		chi sq=255.59	chi sq=4343.43	chi sq=1.71	chi sq=2.7	chi sq=2.13	chi sq=9.42	chi sq=6.65	chi sq=39.33					
4	0	117.5560979	102.042956	178.663777	151.0560774	177.0613086	149.844912	172.5461585	147.4716671					
5	0.05	117.2503156	101.7784678	177.0906577	149.867117	175.6620305	148.793316	171.4109454	146.5565735					
6	0.1	116.9453287	101.5146652	175.5313896	148.687515	174.2738106	147.7491	170.2832011	145.6471582					
7	0.15	116.6411351	101.2515464	173.9858507	147.5171975	172.8965615	146.7122121	169.1628765	144.743386					
8	0.2	116.3377328	100.9891095	172.4539202	146.3560917	171.5301966	145.682601	168.0499227	143.8452219					

Figure 3-33: Time/Luminosity pairs from 0 to 40 hours based on the Equation (1) simple exponential fit values obtained by running the data fitting scripts in this spreadsheet. Parameters for the luminosity equation are take from the "CDF Results" and "D0 Results" workbooks.

	Α	В	С	F	G	Н	I							
	Modified Exponential fit at various times during the store													
1	$L(t) = L_0 e^{-\frac{1}{(\epsilon + \mu t^{\kappa})}}$													
	t Predicted Pred													
2	2 (hours) CDF L(t) D0 L(t) CDF L(t) D0 L(t) CDF L(t) D0 L(t) CDF L(t)													
	from store	Current Fit Init Lum=182 Lifetime=3.33	Current Fit Init Lum=153 Lifetime=4.56	1 hour Init Lum=179 Lifetime=5.6	1 hour Init Lum=152 Lifetime=5.05	2 hours Init Lum=179 Lifetime=4.95	2 hours Init Lum=152 Lifetime=3.23	4 hours Init Lum=179 Lifetime=4.79	4 hours Init Lum=152 Lifetime=4.7					
	Start	u=1.79 a=0.56	u=1.34 a=0.62	u=0.05 a=0.3	u=1.25 a=0.86	u=0.71 a=0.9	u=3 a=0.3	u=0.86 a=0.8	u=1.62 a=0.48					
3		chi sq=1.19	chi sq=455.99	chi sq=1.78	chi sq=0.41	chi sq=1.37	chi sq=0.46	chi sq=1.01	chi sq=0.49					
4	0	181.9231475	153.249986	178.6842912	151.9029727	179.2795953	152.1364258	179.3361761	151.7945806					
5	0.05	179.4605122	151.6502299	177.1024886	150.4348652	177.4949394	150.4369808	177.5040379	150.3073797					
6	0.1	177.2315103	150.1395266	175.5372987	149.0240092	175.7568568	148.9561492	175.7329032	148.9198503					
7	0.15	175.1495501	148.692461	173.9873176	147.6627067	174.061494	147.5756328	174.0139251	147.5942796					
8	0.2	173.1815512	147.298254	172.4520324	146.3463823	172.4063417	146.2648089	172.3422657	146.3173368					

Figure 3-34: Time/Luminosity pairs from 0 to 40 hours based on the Equation (2) modified simple exponential fit values obtained by running the data fitting scripts in this spreadsheet. Parameters for the luminosity equation are take from the "CDF Results" and "D0 Results" workbooks.




Figure 3-35: Time/Luminosity pairs from 0 to 40 hours based on the Equation (3)time decay fit values obtained by running the data fitting scripts in this spreadsheet. Parameters for the luminosity equation are take from the "CDF Results" and "D0 Results" workbooks.



Figure 3-36: Time/Luminosity pairs from 0 to 40 hours based on the Equation (4) modified time decay fit values obtained by running the data fitting scripts in this spreadsheet. Parameters for the luminosity equation are take from the "CDF Results" and "D0 Results" workbooks.

viii. Plots

We generate two different types of plots for each of our luminosity models. The first set of plots show the current store data and the current fits. The second set of data shows how the fit equations change over time. Both types of plots will be shown in the data results section below.

e. VBA Scripts

We have discussed all of the major internals of the Luminosity Predictor spreadsheet. There are portions of the spreadsheet that are complex. The goal is to make the analysis of the data as streamlined as possible, with as little user interaction as possible. To complete this goal, all data analysis occurs by running three VBA Scripts. To analyze our data we simply complete the following:

- Complete the steps in Section 3.c.i, which includes entering a store number, opening the supertable spreadsheet and opening the lumberjack data spreadsheet.
- Run the three VBA scripts outlined below.

No further manual interaction with the spreadsheet is needed. We will now outline our three VBA scripts.

i. <u>Clear All Data Script (Ctrl-Shift-C)</u>

If we are switching our analysis from one store to another store, we want to clear out any old data from other store before we begin. The Clear All Data script completes this task and is launched by pressing Ctrl-Shift-C with the spreadsheet open. This script completes the following steps:

- Clears out all entries in the "CDF_Results" and "D0_Results" workbooks. We are starting over!
- Enters an initial guesses in the "*FitNumbers*" Workbook for each of constants for each of the models. The SuperTable II initial luminosity and luminosity lifetimes are used as the initial guess for those values in each of the fits.

Since this script uses the SuperTable II data, we want to be sure to have completed the steps outlined in Section 3.c.i before running this script.

ii. Analyze the Data Script (Ctrl-Shift-A)

All of the data analysis occurs with the Analyze Data Script, which is launched by pressing Ctrl-Shift-A with the luminosity predictor spreadsheet open. The spreadsheet completes the following tasks.

- Prompts the user with a message box asking how many hours of data to analyze.
 - o Choices include 1, 2, 4, 6, 8, 10, 12, 14, 16, 18, 20, 22, 24, 26, 28 or 30 hours. This option cuts the

- lumberjack data to the number of hours that you specify.
- We can also select all available data, which will make the fit with the entire contents of the lumberjack file. When analyzing a store that is in progress, this will be the most likely option.
- We can also select all data over all times. This
 option is intended to analyze a store after the fact.
 It loops through all data fits at every available time
 slice. Warning, this option normally takes on the
 order of 8 hours to complete.
- Next the user is prompted for which luminosity model to make the fit. Options include the Equation (1) simple exponential fit, the Equation (2) modified exponential fit, the Equation (3) time decay fit, the Equation (4) modified time decay fit, or all four fits. It normally takes on the order of 5 minutes to complete the fit on a single luminosity model and on the order of 20 minutes to complete the fit for all luminosity models.
- Based on the user input, the desired χ^2 calculations from the "*ErrorSums*" workbook are copied to the "*FitNumbers*" workbook.
- Based on the user input, the desired fits are completed for the selected luminosity models over the selected slice in time. This is completed by using the Excel Solver to minimize our χ² calculations by changing the model parameters in the "*FitNumbers*" workbook.
- The results of any data fit(s) completed are then copied over to the "CDF_Results" and "D0_Results" workbooks.

We can now examine out plots and re-run the script to analyze more data from this store. When using this script to look at a store that is still in progress, we simple periodically update our lumberjack data file with the latest data and re-run the analysis until we have enough lumberjack data to be confident of our fit.

iii. Archive (Write) the Data Script (Ctrl-Shift-W)

Once we have completed analysis on one store, we will want to save this data away before we move on to analyzing the next store. The Archive the Data Script completes this task and is called by pressing Ctrl-Shift-W with the Luminosity Predictor spreadsheet open. This script does the following:

a. Archive the store data in a file dedicated to the current store.

- Copies the "values" of each cell in each workbook to the template store-fit-data.xls.
- O Saves the file as **store###-fit-data.xls** (where #### is the store number).
- b. Copy the end of store results to a spreadsheet containing the end of store results for all stores.
 - o Opens the file store-fit-summary.xls.
 - o Creates a new row.
 - Copies the end of store fit data from the "CDF_Results" and "D0_Results" workbooks into the newly created row.
 - Saves and closes the file.

a. Archive Data Files

When we archive our data set via or VBA script, we write to two Excel files. We will briefly mention the function of both files..

i. Individual store{####}-fit-data.xls files

We archive each set of store data in a spreadsheet named store{####}-fit-data.xls. The "value" of each cell from each workbook from the Luminosity Predictor spreadsheet is copied here. The workbook names mirror that of the Luminosity Predictor spreadsheet. The only difference is that we only copy the "values" of the cells. This means the equations and references are not copied, just the results. This allows us to remove the VBA scripts from our archive file and reduce the file size down from 50MB to 12MB. In addition, by removing the calculations, the spreadsheet opens must faster. The plots are left in place so that they can be easily examined later on.

If we want to backtrack and reanalyze the data for this store, or analyze it with more time slices, we can do so fairly easily. We just input the desired store number in the Luminosity Predictor spreadsheets, open the appropriate files, and cut and paste the numbers from the "CDF_Results" and "D0_Results" workbooks in store####-fit-data.xls to the same workbooks in Luminosity-Predictor.xls. The Luminosity Predictor is then ready to go.

ii. Store-fit-summary.xls file

We want to examine results across multiple stores, so there is also a store-fit-summary.xls spreadsheet. Each row in this spreadsheet are the results from one store. The end of store fit numbers for both CDF and D0 using all four Tevatron luminosity models are included in this file. We can use this spreadsheet to plot store data from multiple stores.



Figure 3-37: The summary spreadsheet that contains our fit data for our four luminosity models. Not all columns are displayed due to lack of space.

4. Using the Spreadsheet tool to predict Luminosity

Currently analyzing the data. Results will be posted soon....

5. How luminosity fits improve over time

Currently analyzing the data. Results will be posted soon....




Figure 5-1: Simple Exponential fit at various times in the store.




Figure 5-2: Modified Exponential fit at various times in the store.




Figure 5-3: Time Decay fit at various times in the store.




Figure 5-4: Modified Time Decay fit at various times in the store.

6. How the Luminosity Fits vary from Store to Store

Currently analyzing the data. Results will be posted soon....

7. References and Useful Sources

- 1. McGinnis, Dave. *Recycler-Only Operations Luminosity Projections*. Beams Document Database #2022. http://beamdocs.fnal.gov/cgibin/public/DocDB/ShowDocument?docid=2022.
- 2. McCrory, Elliot. *A Monte Carlo Model of the Tevatron*, Beams Document Database #829. https://beamdocs.fnal.gov/AD-private/DocDB/ShowDocument?docid=829>.
- 3. McCrory, Elliot. *Tevatron Decay Fits*. Home page. 2006. http://mccrory.fnal.gov/tevatronDecayFits/key.html>.
- 4. McCrory, Elliot. *Fitting the Luminosity Decay: Fits and Correlations*. Beam Document Database #1305. < https://beamdocs.fnal.gov/AD-private/DocDB/ShowDocument?docid=1305
- 5. Roman, Steven. *Writing Excel Macros with VBA*, Ed. Warren T. Reich. 4 vols. O'Reily Publishers, 2002.
- 6. Liengme, Bernard V. *Microsoft Excel 2003 For Scientists and Engineers*. Third Edition. Elsevier Butterworth Heinemann, 2004.
- 7. Walkenbach, John. *Microsoft Excel 2000 Power Programming with VBA*. Hungry Minds, Inc. 1999.